

The Imaging Source Helpdesk

[Wissensdatenbank](#) > [Software](#) > [Software für Linux](#) > [Using USB 2.0 CCD cameras in Linux](#)

Using USB 2.0 CCD cameras in Linux

S.Geißler - 2024-01-30 - [Software für Linux](#)

This article effects the cameras

DMK 21AU04, DFK 21AU04, DMK 21BU04, DFK 21BU04

DMK 31AU03, DFK 31AU03, DMK 31BU03, DFK 31AU03

DMK 41AU02, DFK 41AU02, DMK 41BU02, DFK 41AU02

and their .AS astronomy versions.

These cameras like already have an UCV mode but do not inform the operating system about this fact.

Installing udev rules

The udev rules are part of the Github tiscamera repository at <https://github.com/TheImagingSource/tiscamera>

To install the udev rules execute the following commands in :

```
cd tiscamera
sudo cp data/udev/80-theimaging-source-cameras.rules /etc/udev/rules.d/
sudo service udev restart
```

Your system should now correctly identify your camera. Maybe a complete computer start is required.